


1 Tartalomjegyzék


1	Tartalomjegyzék.....	1
2	SqlExpress 2012	2
2.1	Telepítés	2
2.2	Konfigurálás	6
3	Win10 tűzfal beállítások.....	8
3.1	Alkalmazás hozzáadás	8
3.1	Portok engedélyezése	11
4	RefuelFE beállítása	12
5	Sql felügyelet másik gépről.....	13

2 SqlExpress 2012


2.1 Telepítés

Új szerver telepítünk





Alapértelmezéssel tovább



Alapértelmezéssel tovább

SQL Server 2012 Setup

Instance Configuration

Specify the name and instance ID for the instance of SQL Server. Instance ID becomes part of the installation path.

Setup Support Rules
Feature Selection
Installation Rules
Instance Configuration
Disk Space Requirements
Server Configuration
Database Engine Configuration
Error Reporting
Installation Configuration Rules
Installation Progress
Complete

☐ Default instance
☒ Named instance:

Instance ID:

Instance root directory: ...

SQL Server directory:

Installed instances:

Instance Name	Instance ID	Features	Edition	Version
---------------	-------------	----------	---------	---------

< Back Next > Cancel Help

A „Named Instance”-t kell választani

SQL Server 2012 Setup

Server Configuration

Specify the service accounts and collation configuration.

Setup Support Rules
Feature Selection
Installation Rules
Instance Configuration
Disk Space Requirements
Server Configuration
Database Engine Configuration
Error Reporting
Installation Configuration Rules
Installation Progress
Complete


Service Accounts Collation

Microsoft recommends that you use a separate account for each SQL Server service.


Service	Account Name	Password	Startup Type
SQL Server Database Engine	NT Service\MSSQLSQLEXPRESS		Automatic
SQL Server Browser	NT AUTHORITY\LOCAL SERVICE		Disabled

< Back Next > Cancel Help

Alapértelmezéssel tovább




Választani a „Mixed Mode”-t és megadni az „sa” felhasználó jelszavát. PI. RTR-K33-005




Ezzel végetért a telepítés


2.2 Konfigurálás



A konfiguráló program indítása




Engedélyezni kell a TCP/IP használatát



A TCP Dynamic Ports-ot ki kell törölni.


A TCP portot 1433-ra kell állítani






A végén újra kell indítani a szolgáltatást.

3 Win10 tűzfal beállítások

3.1 Alkalmazás hozzáadás










Engedélyezni kell a hálózaton

3.1 Portok engedélyezése



A kijelölt szabályokat engedélyezni kell

4 RefueIFE beállítása



5 Sql felügyelet másik gépről

